

## APPENDIX

```

<?xml version="1.0" encoding="UTF-8"?>
<flextablelist>
  <flextable highlightBackground="153,204,255,255"
5 class="com.enterasys.netsight.atlas.flexview.fvTable" font="dialog-plain-
  11" id="InterfaceFlexView" columnSelectionAllowed="false"
  autoCreateColumnsFromModel="false">
    <tableModel>com.enterasys.netsight.shared.tables.EFTableModel</tableM
odel>
10    <column id="ReqID"
    class="com.enterasys.netsight.atlas.flexview.fvTblCol" fixed="true"
    hidden="true"
    cellRenderer="com.enterasys.netsight.shared.tables.tblCellRend">ReqID
      <notes></notes>
15      <dataField>ReqID</dataField></column>
    <column id="IP Address"
    class="com.enterasys.netsight.atlas.flexview.fvTblCol" fixed="true"
    cellRenderer="com.enterasys.netsight.shared.tables.tblCellRend"
    modelIndex="1">IP Address
20      <notes></notes>
      <dataField>IP Address</dataField></column>
    <column id="Instance"
    class="com.enterasys.netsight.atlas.flexview.fvTblCol" fixed="true"
    cellRenderer="com.enterasys.netsight.shared.tables.tblCellRend"
25    modelIndex="2">Instance
      <notes></notes>
      <dataField>Instance</dataField></column>
    <column id="SNMP;false;2;3;false;false;4"
    class="com.enterasys.netsight.atlas.flexview.fvTblCol" modelIndex="3">Index
30      <notes></notes>
      <dataField>ifIndex</dataField></column>
    <column id="SNMP;false;2;4;false;false;4"
    class="com.enterasys.netsight.atlas.flexview.fvTblCol" modelIndex="4">Type
35      <notes></notes>
      <dataField>ifType</dataField></column>
    <column id="SNMP;false;4;5;false;false;4"
    class="com.enterasys.netsight.atlas.flexview.fvTblCol"
    modelIndex="5">Address
40      <notes></notes>
      <dataField>ifPhysAddress</dataField></column>
    <column id="SNMP;false;15;6;false;false;4"
    class="com.enterasys.netsight.atlas.flexview.fvTblCol"
    modelIndex="6">Description
45      <notes></notes>
      <dataField>ifDescr</dataField></column>
    <column id="SNMPW;false;2;7;true;false;4"
    class="com.enterasys.netsight.atlas.flexview.fvTblCol"
    modelIndex="7">Logical Status
50      <notes></notes>
      <dataField>ifAdminStatus</dataField></column>
    <column id="SNMP;false;2;8;false;false;4"
    class="com.enterasys.netsight.atlas.flexview.fvTblCol"
    modelIndex="8">Physical Status
55      <notes></notes>
      <dataField>ifOperStatus</dataField></column>
    <notes></notes>
    <dataField>0;0;true;30;ifEntry;V.0.0.0.2;0</dataField></flextable></f
lextablelist>

```